

LM-X End-user utility

The information on this page refers to LM-X v5.4.1 or newer, which added the "-verifyauth" command and introduced brute-force password protection. If you are using a previous version of LM-X, please see the [documentation for previous versions](#).

The LM-X End-user utility lets you get the HostID values for the computer system. For machine-locked licenses, application vendors will use HostID values to create licenses specifically for your system. The LM-X End-user utility also lets you:

- See who is currently using specific licenses on the license server, and see the borrow, grace and trial licenses currently checked out
- Remotely access the license server
- Remove users from the license server
- Read and verify a usage database and print the usage information to the screen

The LM-X End-user utility may be run by any user; you do not need administrator privileges to run the utility. The `lmxendutil` command usage is as follows. Optional parameters are enclosed in square brackets (`[]`). Variables are shown in *italic text*.

Command	Syntax	Description
-hostid	<code>lmxendutil -hostid</code>	Displays HostID values of your computer system.
-licstat	<code>lmxendutil -licstat [-vendor <vendor_name> (-host <host> -port <port> -hal <servers>) -network -borrow -grace -trial -denials]</code>	Displays statistics and lists which users are currently using which licenses on a specific license server Note: The <code>lmxendutil -licstat</code> command does not use the environment variable <code>LMX_LICENSE_PATH</code> when querying the license server. A client application can find license servers on the network automatically, using automatic server discovery or the <code>-host</code> option. When <code>-vendor</code> is used, the statistics will be limited to the specified vendor. If <code>-vendor</code> is not used, information such as grace, borrow and trial checkouts may not be returned, because the vendor is unknown. Information for the borrow, grace and trial licenses currently checked out is also returned unless one or more options are specified; for example, specifying <code>-borrow</code> will result in only borrow information being returned. If the <code>-denials</code> option is specified, this command additionally prints detailed information about denials for current and disconnected users for the past 24 hours, including username, hostname, IP address, login times, and denial times. See below for descriptions of optional parameters <code>-hal</code>, <code>-host</code>, and <code>-port</code>.
-licstatxml	<code>lmxendutil -licstatxml [-vendor <vendor_name> (-host <host> -port <port> -hal <servers>) -network -borrow -grace -trial -denials]</code>	Displays the same information as for <code>-licstat</code> , but in XML format.
-restartserver	<code>lmxendutil -restartserver [-host <host> -port <port> -password <password>]</code>	Remotely restarts the license server. See below for descriptions of optional parameters <code>-host</code>, <code>-port</code> and <code>-password</code>.
-shutdownserver	<code>lmxendutil -shutdownserver [-host <host> -port <port> -password <password>]</code>	Remotely shuts down the license server. See below for descriptions of optional parameters <code>-host</code>, <code>-port</code> and <code>-password</code>.
-readusagedb	<code>lmxendutil -readusagedb <usage.db></code>	Reads the specified usage database and performs a verification, then prints the usage information to the screen. (See Pay Per Use feature .)
-removeuser	<code>lmxendutil -removeuser -clientusername <username> -clienthostname <hostname> [-feature <feature> [-version <version>] -host <host> -port <port> -password <password>]</code>	Removes a user from the license server. Parameter descriptions are as follows: <code>-clientusername <username></code> Removes a user with the specified username. <code>-clienthostname <hostname></code> Removes a user at the specified hostname. See below for descriptions of optional parameters <code>-host</code>, <code>-port</code>, <code>-password</code> and <code>-feature [-version]</code>.
-verifyauth	<code>lmxendutil -verifyauth -host <host> -port <port> -password <password></code>	Verify the license server's credentials on the current or a foreign host.

Optional parameters

Command	Syntax	Description
---------	--------	-------------

-hal	-hal <i>server1 server2 server3</i>	Optional parameter for specifying HAL servers, used only when HAL is enabled. You must specify three servers in <i>port@host</i> format; for example: Imxendutil -licstat -vendor VENDORNAME -hal 6200@localhost 6300@localhost 6400@localhost Imxendutil -licstatxml -vendor VENDORNAME -hal 6200@localhost 6300@localhost 6400@localhost
-host	-host <i>host</i>	Optional parameter that connects to the specified license server host. If you don't specify the -host option, Imxendutil command will perform autodiscovery.
-port	-port <i>port</i>	Optional parameter that connects to license server on port 'myport'. If you do not enter this optional parameter, the default port is used.
-password	-password <i>password</i>	Optional parameter that uses the specified password. If you do not use this optional parameter explicitly, you will be prompted for the password (in this case, the password you enter is not displayed on the screen as you type). Note that LM-X uses brute force password protection to prevent brute-force attacks.
-feature [-version]	-feature <i>feature</i> [-version <i>version</i>]	Optional parameter for use with -removeuser command that limits user removal to a specified user/host who has checked out a specified feature. For example: Imxendutil -removeuser -clientusername <i>username</i> -clienthostname <i>hostname</i> -feature <i>feature</i> [-version <i>version</i>]