


# Linux installation using RPM installer

*The information on this page refers to License Statistics v6.21 or newer, which removed the lacutil tool. If you are running a previous version of License Statistics, see [documentation for previous versions](#).*

This section describes the installation procedure for Linux using the RPM installer, which is recommended for use with RedHat Enterprise Linux.

 Administrator privileges are required for installation.

## Installation

1. Download the License Statistics installation from the [License Statistics download page](#).
2. Run the installer from a command line:

```
sudo rpm -i {rpm_file}
```

For example:

```
sudo rpm -i xflicstat-6.17.0-1.x86_64.rpm
```

```
[root@localhost ~]# rpm -i xflicstat-6.17.0-1.x86_64.rpm
Created symlink /etc/systemd/system/multi-user.target.wants/xflicstat.service → /usr/lib/systemd/sy
tem/xflicstat.service.
[root@localhost ~]#
```

## File structure

Files related to the RPM installation are located in the following directories.

File	Description
/opt/xflicstat	Application files
/var/opt/xflicstat	User files, including logs and stored data
/etc/default/xflicstat	Package parameters

## Configuration

Configure the installation using the configuration file:

/opt/xflicstat/conf/xflicstat.cfg

## Activating the license

License files must be placed in /var/opt/xflicstat/license directory.

1. Go to the directory:  
/var/opt/xflicstat/license
2. Run the xflicstat-cli tool:  
/opt/xflicstat/bin/xflicstat-cli license activate *activation\_key*

You may also use an alternative activation method, as described in [Activating a License Statistics license](#).

## Starting the service

1. Start the service from a command line:

```
sudo service xflicstat start
```

2. Access License Statistics in the browser:

```
{hostname}:80
```

```
[root@localhost license]# service xflicstat start
Redirecting to /bin/systemctl start xflicstat.service
[root@localhost license]# service xflicstat status
Redirecting to /bin/systemctl status xflicstat.service
• xflicstat.service - An application that monitors, processes and produces reports on software lice
  Loaded: loaded (/usr/lib/systemd/system/xflicstat.service; enabled; vendor preset: disabled)
  Active: active (running) since Thu 2022-12-29 09:51:18 EST; 9s ago
    Docs: https://docs.x-formation.com/display/LICSTAT
   Main PID: 2144 (xflicstat)
      Tasks: 65 (limit: 4620)
     Memory: 569.2M
        CPU: 5.168s
    CGroup: /system.slice/xflicstat.service
            └─2144 /opt/xflicstat/bin/xflicstat --run --logDir /var/opt/xflicstat/log --licenseDir
              └─2151 /opt/xflicstat/bin/xflicstat --run --logDir /var/opt/xflicstat/log --licenseDir
                └─2160 /opt/xflicstat/embedded/bin/mysqld --defaults-file=/opt/xflicstat/embedded/etc/
                  └─2218 /opt/xflicstat/embedded/jre/bin/java -Xmx2048m -Xms512m -Djava.library.path=cor
Dec 29 09:51:18 localhost.localdomain systemd[1]: Started An application that monitors, processes a
lines 1-15/15 (END)
```

## Stopping the service

Stop the service from a command line:

```
sudo service xflicstat stop
```

## Removing the service

Uninstall the service, but keep user and configuration files for future usage:

```
sudo rpm -e xflicstat
```

## Updating the service

To update the service (introduced as of v6.17):

1. Download the License Statistics installation from the [License Statistics download page](#).
2. Run the installer from a command line:

```
sudo rpm -U {deb_file}
```