XML file examples

The following are examples of XML files for floating and node-locked licenses, and a more detailed example including multiple features and additional, optional settings. These examples are included as sample files in the LM-X distribution, so you can modify the file that most closely fits your needs.

Node-locked license example

The following shows an example of the XML file content for a node-locked license with a single feature (sample file nodelocked.xml). Note that the CONFIGFILE and OUTPUTFILE settings can be specified either within the file or at the command line (see Generating licenses).

Floating network license example

The following shows an example of the XML file content for a floating license with a single feature (sample file floating.xml).

Note that:

- The COUNT setting is included, which identifies this as a floating license.
- The CONFIGFILE and OUTPUTFILE settings can be specified either within the file or at the command line (see Generating licenses).
- The feature's version number is not specified, so it will default to 1.0.

Detailed license example

The following shows an example of the XML file content for a floating license with multiple features, plus many of the optional settings such as license sharing, borrowing, etc. (sample file detailed.xml).

```
<LICENSEFILE CONFIGFILE="myprogram.lmx" OUTPUTFILE="detailed.lic">
<!-- You can put comments into the header of the license if needed -->
<LICENSEFILE COMMENT="This license was created by the xml based license generator."/>
<LICENSEFILE COMMENT="You could use this space to explain the type of license you are providing."/>
 <FEATURE NAME= "f2">
   <SETTING START="20013-12-24"/>
   <SETTING END="2015-12-25"/>
   <SETTING MAJOR_VERSION="1"/>
   <SETTING MINOR_VERSION="3"/>
   <SETTING LICENSEE="our_user"/>
   <SETTING COMMENT="Our_product_setting_values"/>
   <SETTING KEYCOMMENT="hidden text retrieved from API"/>
   <SETTING SHARE="TERMINALSERVER"/>
   <CLIENT_HOSTID>
   <SETTING ETHERNET="C8A516AD01AFC9FA"/>
   </CLIENT HOSTID>
   <CLIENT_HOSTID>
   <SETTING CUSTOM="C8A516AD01AFC9FB"/>
   </CLIENT_HOSTID>
 </FEATURE>
 <FEATURE NAME= "f1">
   <SETTING END="2016-01-01"/>
   <SETTING MAJOR_VERSION="1"/>
   <SETTING MINOR_VERSION="5"/>
   <SETTING LICENSEE="Our_valued_customer"/>
   <SETTING COUNT="10"/>
   <SETTING SHARE="HOST"/>
   <SETTING SHARE="USER"/>
   <SETTING BORROW="100"/>
   <SERVER_HOSTID>
   <SETTING ETHERNET="C8A516AD01AFC9FA"/>
   <SETTING CUSTOM="C8A516AD01AFC9FB"/>
   </SERVER_HOSTID>
 </FEATURE>
</LICENSEFILE>
```

Note that the CONFIGFILE and OUTPUTFILE settings can be specified either within the file or at the command line (see Generating licenses).